

DEPLOYMENT GUIDE

1. Calibrate



- Calibrate your spray equipment
- Use larger than D1 nozzles
- Use screens coarser than 50 mesh
- Do not use gear or roller pumps

2. Calculate



- CheckMate® VMB-F recommended application rate is 0.9 fl. oz. per acre
- VMB-F can be sprayed at very low volumes, as well as higher, usual volumes. Run off should always be avoided

3. Prepare



- Shake vigorously as separation is common
- If contents are not fluid, strike bottle on a hard surface until the crust breaks apart, then shake vigorously

4. Mixing



- Partially fill the tank before mixing
- Other products can be mixed with VMB-F. These products should be added first before VMB-F

5. Measure & Mix



- Measure the amount of VMB-F needed and add to the tank last
- Triple rinse the empty bottles and dump rinses into the mixing tank
- Maintain constant agitation once mixed to prevent separation

6. Spray



- Begin the spray application
- VMB-F is compatible with both ground and aerial applications
- VMB-F effects are immediate

L17998 VMB-F FG 16667-US Rev05182021



© 2020 Suterra LLC. All rights reserved. Suterra®, CheckMate® and the accompanying logos are trademarks of Suterra LLC. No part of this document may be reproduced, distributed, or transmitted in any form or by any means, including photocopying, recording, or other electronic or mechanical methods, without the prior written permission of Suterra LLC.

Watch our
Deployment Guide Video



GUÍA DE APLICACIÓN

1. Calibrar



- Calibre su equipo de pulverización
- Utilice boquillas D1 o de mayor tamaño
- Utilice mallas 50-mesh o de grano más grueso
- No utilice bombas de engranaje o rodillo

2. Calcular



- La dosis recomendada de CheckMate® VMB-F es de 0.9 fl. oz. por acre
- VMB-F puede pulverizarse a volúmenes bajos o volúmenes mayores más usuales. Evitar llegar al punto de goteo

3. Preparar



- Agite vigorosamente y no deje reposar, ya que se produce separación con facilidad

4. Mezclar en el tanque



- Rellene parcialmente el tanque antes de mezclar
- Si va a mezclar VMB-F con otros productos, añada los productos compatibles al depósito antes que VMB-F
- Consulte la guía de compatibilidad de Suterra

5. Medir y mezclar



- Mida la cantidad de VMB-F necesaria y añádala al tanque en último lugar
- Enjuague tres veces las botellas vacías y vierta el agua de los enjuagues en el tanque
- Mantenga una agitación constante una vez mezclado para evitar la separación

6. Pulverización



- Inicie la pulverización de manera inmediata
- VMB-F es compatible tanto con aplicaciones aéreas como terrestres
- Los efectos de VMB-F son inmediatos

L17998 VMB-F FG 16667-US Rev05182021



The use of Mating Disruption tools should be part of an overall Integrated Pest Management (IPM) program. The use of other pest control measures may be necessary and should be based on proper pest monitoring and field scouting.

Watch our
Deployment Guide Video

